



MOSAIC SCREENS

Setup MOSAIC screens

Copyright © 2018 DUALZ SOFTWARE BV

ALL RIGHTS RESERVED

INFORMATION IN THIS DOCUMENT IS PROTECTED AND CAN NOT BE
REPRODUCED IN ANY FORM WITHOUT THE PERMISSION OF
DUALZ SOFTWARE BV.

CONTENTS

| | |
|------------------------------|---|
| Introduction | 3 |
| Installation | 3 |
| Installation procedure | 3 |
| Configuration | 3 |
| Configuration folder | 3 |
| Screen configurator | 3 |
| Shortcuts..... | 4 |

INTRODUCTION

This document describes how to setup MOSAIC screens. This configuration is done only once, and doesn't need any changes, if the number of screens or their location does not change.

INSTALLATION

INSTALLATION PROCEDURE

Install Multiviewer Blocks msi: SetupMultiviewerx.y.z.msi
If a previous installation was done on your system, please uninstall that instance first.

CONFIGURATION


CONFIGURATION FOLDER

During installation the configuration directory needs to be created on the mosaic server, recommended "C:\MosaicBlocks". This folder keeps all the data that is needed to configure the screens setup.

SCREEN CONFIGURATOR

The screen configurator can be started via:
Program menu -> Dualz Software BV -> MOSAIC screen configurator

The following form is shown:




It is important to enter the correct Configuration folder (that was entered during startup).

The Application folder is the installation folder of the Multiviewer (player).

Screens can be added, removed or edited.

Per screen, the following settings can be given:

A screenshot of a software dialog box titled "Edit mosaic screen". The dialog has a close button (X) in the top right corner. It contains four input fields: "Name" with the text "Penalty box", "Location" with sub-fields for "X" and "Y" both containing "0", "Management IP" with the text "127.0.0.1", and "Port" with the text "2004". At the bottom, there are two buttons: "Save" and "Cancel".

Name: Name of the screen

Location: Location on your windows desktop, can be on extended monitor, for example (1920,0).

Management IP: The management network IP address, the editor must be in the same LAN. If the editor runs locally (on the same system), localhost 127.0.0.1 can be used here.

Port: Network port, used for communication with the editor, must be unique per system.

SHORTCUTS

During saving the screen list, the screen configurator shall request for saving shortcuts to the desktop. With these shortcuts the screens can easily be started, or added to the startup folder, in order to start automatically after system startup.